Documentation


XIQ-SE Workflow "NAC ES name to switch port alias"

Assign NAC End System Name to the switch port. The data from the Control End System Table and the MAC address description from the End System Group Definition are used. If an end device IP address is available, a DNS reverse lookup is performed to determine the FQDN. If DNS cannot resolve the FQDN, the alias from the MAC address description is used. Finally, the port alias is developed which should normally be the FQDN hostname. Several hosts are supported on one port and used as a comma-separated alias. The length of the port alias is limited to 64 characters. If the intended alias is longer, it is shortened to 64.

Software & hardware used:

- XIQ-SE 25.02
- Control
- Fabric Engine

Once the workflow has been imported, it can be executed. A dialogue is presented to the user, which should be adjusted accordingly.



Site Path:

is a filter for limiting the quantity of switches to be used.

Days to review:

This is the number of days that the registrations are viewed in the End System table. Days looking back from midnight.


write Debug LOG:

This parameter is used for troubleshooting. If it is **true**, the file system of the XIQ-SE under **/dev/shm/** will be folder created, which use the Execution ID followed by the Workflow name. This directory contains a LOG file and corresponding JSON data for each activity.


Sanity check:

This is a test run where all functions are executed except for configuring the switch.


It is useful to run the workflow once a day via the schedule service. You can set this up by starting the workflow and entering the following in the second dialogue window.




If the setup was successful, you will find the following entry.




Optionally, it is possible to use the description of the MAC address as a fallback if the DNS FQDN is not given. To do this, the parameter **ES_DESCRIPTION** must be set to **true**.



If this is the case, the description is used as in the example below.



It is also possible to optionally set the port information before the host name. This can be useful for various monitoring software. If the parameter **PORT_ALIAS** is set to **true**, the feature is active.



As an example Win11-7 then the alias will beset to 1/6_Win11-7.

Troubleshooting

Finally, before reporting an issue, please ensure that the workflow is configured for **DEBUG** mode. The data and debug LOG files can then be found on the XIQ-SE file system under /dev/shm/_<Workflow-Name>">/ . Note that only the last six execution debug logs will be held. The actual path can also be found in the each workflow activity log.

```
Output

Script Name: NAC_ES_name_to_port_alias_read
Date and Time: 2025-03-20T09:25:22.299
XIQ-SE User: mnikulski
XIQ-SE User Domain:
IP:
09:25:26 INFO LOG file /dev/shm/2230 Workflows_CTC-Production_NAC_ES_name_to_port_alias/read.log
09:25:26 INFO pull 40 records from End System Table
09:25:26 INFO host None with MAC 00:50:56:86:72:4A on switch 20.0.209.15 port 2:5 [2005]
09:25:26 INFO host None with MAC 00:50:56:86:72:4A on switch 20.0.209.15 port 2:5 [2005]
```

When SSH-ing XIQ-SE, the following log files should be present in the folder.

Please include all log files when reporting an issue.